

Autostore - Scan naar Mail

- Basis scherm instellingen

Form Settings

General Fields Components

Name:

☐ Single Touch mode

Access Control

☒ Public Access

☐ Restricted Access

Allowed Users/Groups:

Scanning Settings

Setting	Options	Allow Changes
File Format	TIFF	☐
Resolution	200 dpi	☐
Color Mode	Full Color	☐
Color Document Quality	Medium	☐

Default Encrypted pdf password:

Dynamic Form

☐ Enable Dynamic Form

Script Path:

Edit Script Code...

Raise event when:

☐ Form is loaded


☐ Form is submitted

☐ Run as device logged in user

OK Cancel Help



- Mail adressen toevoegen of verwijderen

1. Ga naar het tabblad Fields.
2. Klik op de properties knop achter Adresboek of CC.
3. Verwijder of voeg mail adressen toe.




- Mail settings configureren

1. Ga naar tabblad Components.
2. Klik op properties knop achter Multi Router.




3. Wijzig de From, To, Cc, Subject, Schema en gebruik de RRTs om variables te gebruiken, gebruik Sharp MFP OSA voor de gewesnte variables.
4. Wijzig de Schema en gebruik de RRTs om variables te gebruiken, gebruik Attachment voor de gewesnte variables.



- Instellingen opslaan

1. Klik overal nu op Ok
2. Klik in de tool bar op restart om de gewijzigde instellingen door te voeren



Unieke FAQ ID: #1366

Auteur: Helpdesk

Laatst bijgewerkt: 2015-06-09 16:17